

rk

Hi Guys

If you have come across the following error condition Target Node/ Queue Unavailable and you are not able to start the Standard manager or Internal Monitor / Internal Manager is in the Activating status forever please read on.

Various metalink documents have given various solutions. I have given them in the rank.

1) set the profile option value Concurrent:GSM Enabled to NO.

2) In the hosts file the following should be the syntax

```
IP          domain name          hostname
127.0.01   rk.orafinapps.com       hostname
```

My computername is rk domain name orafinapps.com  
and hostname is rk.orafinapps.com

Change these according to ur situation.

I also ran the following queries.

```
3) update fnd_concurrent_requests
set status_code='X', phase_code='C'
where status_code='T';
```

```
4) update fnd_concurrent_queues
      set control_code = 'A'
      where concurrent_queue_name = 'FNDCRM';
```

```
5) UPDATE fnd_concurrent_requests
      SET phase_code = 'C'
      WHERE phase_code = 'P'
```

```
6) delete from fnd_dual where rownum < (select max(rownum) from fnd_dual)
```

-- use the hostname in the following query"

```
7) update FND_CONCURRENT_QUEUES
      set control_code = null
      where concurrent_queue_name = 'OAMGCS_<node name>'; -- supply the node name
here
```

This resolved my issue.

Any one or more than solutions might fix your problem. So pl test each solution and if it fixes your solution.

Otherwise the whole set has worked for me.

So save time and your efforts by following the solution.

Thanks  
RK